



Setting up your OPOS Cash Drawer

This section is dedicated to guiding you through the setup process of an Epson OPOS Cash Drawer connected directly to your Epson TM-T88ii USB printer

Add Cash Drawer

- 1. If OPOS is not open, start it from your "Start" menu in Windows.
- 2. Click Start > OPOS > SetupPOS ver2.00
- 3. Right click CashDrawer and click Add New Device

Note: The steps here were conducted with an Epson Cash Drawer with a 6-pin RJ Connector.

Note: If you have an Epson Cash Drawer with a 6-pin RJ Connector, you must connect the cash drawer to the back of the receipt printer now.



4. Right click CashDrawer & add new device

Standard	▼ StandardU ▼
🗖 Display Ver1.xx 🔽 Display Ver2.xx	Used Port
Device Description	USB
Standard Cash Drawer(USB) for EPSON TM se	eries
NF File Name.	
C:\PROGRA~1\0P0S\Epson2\CrStand.inf	Browse
d New LDN	
Set up a logical device name if necessary.	
* A logical device name isn't indispensable. A logical device name isn't set up in the cas And, a logical device name can be set up en	e as the blank. ven later.
EPSONCASH	
]	

5. Select the type of the cash drawer (StandardU) you are using from combo box of available devices.

There are four options available:

Standard: Select this option if your cash drawer is connected to a serial port POS Printer

StandardP: Select this option if your cash drawer is connected to a parallel port POS Printer

StandardU: Select this option if your cash drawer is connected to a USB port POS Printer

StandardE: Select this option if your cash drawer is connected to an Ethernet POS Printer

6. Now that the correct model has been added, you can now proceed to renaming the LDN to EPSONCASH and then click NEXT.

	USB1 💌	Port is being used by	
	Auto Settings	(None)	_
Setup of details	of the port.		
Baud <u>R</u> ate	_	InputBuf	
BitLength	_	⊡utputBuf	
Parity	Ţ	Output Inter <u>v</u> al Time	500 msec
StopBit	_	Input Sl <u>e</u> epTime	msec
Han <u>d</u> shake	<u> </u>		
Check	Health Interactive	Device Speci	fic Settings

7. Ignore all other options on the above dialogue, Click on Check Health Interactive,

If successful the following dialogue box will display.



8. Click Finish, your cash drawer is now setup and ready for use.

If unsuccessful the following dialogue box will display.

	Error occurred in calling the CheckHealth method:	
-	SetDeviceEnabled(True) = 106 (0x0000006a)	
	ResultCodeExtended = 10002 (0x00002/12)	

You will then have to go back unplug everything and start from Step 1.